



Getting started with GearShift

Installing the application:


1. Download and extract "**GearShiftTechnologies.zip**" to Desktop or any other folder of your choice.




2. After extracting there should be 3 subfolders in "**GearShiftTechnologies**" select "**GearShift Technologies**" folder and copy to "**C:\Program Files**".




3. To create a shortcut on Desktop, locate "**GearShift.exe**" in "**C:\Program Files\GearShift Technologies\GearShift Ultimate Edition**" and right click on "**GearShift.exe**" and select "**send to**" click on "**Desktop (create shortcut)**".



4. Copy Data folder, from extracted folder open "**ApplicationData**" and copy "**GearShiftData**" folder to "**C:\ProgramData**". Can't find "**ProgramData**" folder, skip this step and go to step 5.




5. Some applications "hide" essential files in folders that are hidden by default in the Windows Operating System. To view the "**ProgramData**" folder, click on "**View tab**" and tick the "**hidden items**" box in the "**show/hide**" section. Go back to "**Step 4**".




Installing Device Drivers:


1. To install the drivers on windows 10, **driver signature enforcement** must be disabled. Read/Print "How to Disable driver signature enforcement.pdf" document and follow the steps.
2. Open "Device Manager" ("Windows key + x" and select Device manager) and plug in the device, under "**other devices**" right click on "**Unknown Device**", then click on "**Update driver**" and then select "**Browse my computer for driver software**".





- Click on "**Browse**", select "**GearShift_Drivers**" folder and click OK, then click next, a security message will pop up click "**install this driver software anyway**" and wait while the wizard completes the installation.




- Repeat step 2, then click on "**Browse**", select "**Decoder_Drivers**" folder and click OK, then click next, a security message will pop up click "**install this driver software anyway**" and wait while the wizard completes the installation.




5. To install CAN communicator drivers, plug in device, under "Universal Serial Bus devices" right click on "Enigma CAN Interface PRO" then click on **"Update driver"**, then select **"Browse my computer for driver software"** and then click on **"Let me pick from a list of available drivers on my computer"**.



- 5.1. After that click **"Have disk"**, then click **"Browse"**, locate and select **"CAN Communicator.inf"** file **"GearShiftTechnologies\USB_Drivers\CAN_USB_Drivers"** then click **"Open"** and then click **"OK"**. Now select **"CAN Communicator"** under **"Model"**, click **"Next"** and a security message will pop up click **"install this driver software anyway"** and wait while the wizard completes the installation.



6. Once the installation is complete all the devices will appear under "**Gear box system testers**".



Having trouble installing device drivers, please contact us.

Important Notes: Application Data must be copied correctly to "**C:\ProgramData**" or the software will not Work.

Contact details:

Email: office@gearshifttechnologies.com

Tel: 01283521414